

## Data Declaration System

What's new in Version 13.3?

Dec 1<sup>st</sup> 2017

### DDS Contact

email: [hotline@visu-it.com](mailto:hotline@visu-it.com)

Internet: <http://www.visu-it.de/DDS>



© Copyright 2017

Visual Information Technologies GmbH

An der Schergenbreite 1

93059 Regensburg

## Contents

<b>1 Purpose and scope .....</b>	<b>3</b>
<b>2 What's new in Version V13.3.R1?.....</b>	<b>3</b>
<b>2.1 Features.....</b>	<b>3</b>
<b>2.2 Improvements / Correction of Bugs .....</b>	<b>3</b>
ImpADD .....	3
<b>3 What's new in Version V13.3.R0?.....</b>	<b>3</b>
<b>3.1 Features.....</b>	<b>3</b>
ExpA2.....	3
GenEdit.....	3
ImpADD .....	3
ImpELF .....	3
<b>3.2 Improvements / Correction of Bugs .....</b>	<b>3</b>
ExpA2.....	3
ImpA2 .....	3
<b>4 No longer supported filters/components .....</b>	<b>4</b>
<b>5 Questions?.....</b>	<b>4</b>

## 1 Purpose and scope

This document describes the improvements and changes made in DDS V13.3.

## 2 What's new in Version V13.3.R1?

Improvements and changes of DDS V13.3.R1 compared to previous.

### 2.1 Features

### 2.2 Improvements / Correction of Bugs

#### ImpADD

- Bugfix option "UseMaxRefresh4OnlineUpdate": Controls whether the TimePeriod of the AccessFrequency or the MaxRefresh is taken into account, to create an onlineUpdate.

## 3 What's new in Version V13.3.R0?

Improvements and changes of DDS V13.3.R0 compared to previous.

### 3.1 Features

#### ExpA2

- Support of new protocol "XCPplus V1.4"

#### GenEdit

- New field for SymbolLink-Address.

#### ImpADD

- New Option "UseMaxRefresh4OnlineUpdate": Controls whether the TimePeriod of the AccessFrequency or the MaxRefresh is taken into account, to create an onlineUpdate.

#### ImpELF

- Reworked SymbolLink address import to improve flexibility and get rid of various limitations. E.g. multiple SymbolLinks can point to the very same entity. SymbolLinks can point into incomplete modelled structures in DDS, etc.

### 3.2 Improvements / Correction of Bugs

#### ExpA2

- Newly conversions from an a2l file that must be copied to an equivalent "isReal" conversion (the isReal attribute set to true) now have set proper limits before copying.

#### ImpA2

- Supports of correct A2L version 1.6.0 ident length limits (1024 characters).

## 4 No longer supported filters/components

## 5 Questions?

If you have any questions about this release, please contact the Visu-IT! DDS Hotline:

### DDS Hotline

Tel.: +49 (0)941 / 49082 - 16  
email: [hotline@visu-it.com](mailto:hotline@visu-it.com)



### DDS Product page

Internet: <http://www.visu-it.de/DDS>